

ACRC Hands On Exercise List

This web site and the materials offered herein are neither affiliated with nor endorsed by Cisco Systems Inc. "Cisco," "CCIE," "CCNA," "CCNP," "CCDP," "CCDA," "Cisco Certified Network Associate," "Cisco Certified Network Professional," "Cisco Certified Design Associate," and "Cisco Certified Design Professional" are trademarks owned by Cisco Systems Inc.

This material is licensed for use by people with accounts in good standing at www.networkstudyguides.com, please do not redistribute or share with others. Please report any illegal distribution of this material to piracy@digitalco.com

Configuring Transparent Bridging

1. assign a bridge group and define a spanning tree protocol
router(config)#bridge 1 protocol ieee
2. assign each network interface to the bridge group
router(config)#interface ethernet 0
router(config-if)#bridge-group 1
3. (optional) set the bridge priority
router(config)#bridge 1 priority 10
4. (optional) set the interface path cost
router(config-if)#bridge-group 1 path-cost 10

Configuring Source Route Bridging

For Dual Port Bridge

1. Enable SRB on the appropriate Token Ring interface
source-bridge local-ring bridge-number target-ring
Router(config-if)#source-bridge 10 1 15

For Multiport Bridge

1. Define a ring group
source-bridge ring-group ring-number
router(config)#source-bridge ring-group 7
2. Enable SRB on the appropriate Token Ring interfaces
source-bridge local-ring bridge-group target-ring
Router(config-if)#source-bridge 10 1 7

Configuring SRT

1. enable both transparent and source route bridging on interfaces
router(config)#bridge 1 protocol ieee
router(config)#source-bridge ring-group 7
router(config)#interface tokenring 0
router(config-if)#bridge-group 4
router(config-if)#source-bridge 500 1 7
router(config)#interface tokenring 1
router(config-if)#bridge-group 4
router(config-if)#source-bridge 501 1 7

Configuring Source Route Translational Bridging

1. Router must be completely configured for Transparent and SRB routing
Router(config)#source-bridge ring-group 7
Router(config)#bridge 4 protocol ieee
Router(config)#interface tokenring 0
Router(config-if)#source-bridge 500 1 7
Router(config-if)#source-bridge spanning

```

Router(config)#interface tokenring 1
Router(config-if)#source-bridge 501 1 7
Router(config-if)#source-bridge spanning
Router(config)#interface ethernet 0
Router(config-if)#bridge-group 4
2. Establish bridging between transparent and SRB
Source bridge transparent ring-group pseudo-ring bridge-number tp-group
Router(config)#source-bridge transparent 7 13 1 4

```

Configuring Integrated Routing and Bridging

1. enable irb
router(config)#bridge irb
2. select a spanning tree protocol
router(config)#bridge 10 protocol ieee
3. enable routing on routed protocols
router(config)#bridge 10 route appletalk
router(config)#bridge 10 route ip
4. disable bridging on routed protocols
router(config)#no bridge 10 bridge ip
5. assign bridge groups to interfaces
router(config)#interface ethernet 0
router(config-if)#bridge-group 10
6. enable bvi
router(config)#interface bvi 10

Configuring Priority Queuing

1. create the list in global config mode
router(config)#access-list 2 permit 131.108.0.0 0.0.255.255

router(config)#priority-list 1 protocol ip high tcp 23
router(config)#priority-list 1 protocol ip high list 2
router(config)#priority-list 1 interface ethernet 0 medium
router(config)#priority-list 1 protocol appletalk medium
router(config)#priority-list 1 protocol ipx medium
router(config)#priority-list 1 protocol ip normal
router(config)#priority-list 1 default low
router(config)#priority-list 1 queue-limit 15 20 20 20
2. apply the list in interface mode
router(config)#interface serial 0
router(config-if)#priority-group 1

Configuring Custom Queuing

1. create the list in global config mode
router(config)#queue-list 1 protocol ip 1 tcp 20
router(config)#queue-list 1 interface ethernet 0 2
router(config)#queue-list 1 protocol ip 3
router(config)#queue-list 1 protocol ipx 4
router(config)#queue-list 1 protocol appletalk 5
router(config)#queue-list 1 default 6
router(config)#queue-list 1 queue 1 byte-count 4500
2. apply the list to a specific interface
router(config)#interface serial 3
router(config)#custom-queue-list 1

Limit Virtual Terminal Access

1. generate access list in global config mode
router(config)#access-list 12 permit 192.89.55.0 0.0.0.255
2. apply access list in line interface mode
router(config)#line vty 0 4
router(config-line)#access-class 12 in

Configure IP Standard Access List

1. generate access list in global config mode
router(config)#access-list 1 permit 172.16.0.0 0.0.255.255
2. apply access list in interface mode
router(config)#interface ethernet 0
router(config-if)#ip access-group 1 in

Configure IP Extended Access List

1. generate the access list in global config mode
router(config)#access-list 100 permit tcp any 128.88.0.0 0.0.255.255 established
router(config)#access-list 100 permit tcp any host 128.88.1.2 eq smtp
router(config)#access-list 100 permit udp any eq domain any
router(config)#access-list 100 permit icmp any any echo
router(config)#access-list 100 permit icmp any any echo-reply
2. apply access list in interface mode
router(config)#interface ethernet 0
router(config-if)#ip access-group 100 in

Verify Access List Operation

- show access-list
- show ip access-list list-number
- clear access-list counters list-number
- show line

Configure an Alternative to Access Lists

1. assign a static route to a null interface, causing the packet to be discarded.
Router(config)#ip route 172.16.1.0 255.255.255.0 null 0

Configure an IP Helper Address

- ip helper-address – forwards 8 UDP ports automatically. TFTP (69), DNS (53), Time (37), NetBIOS name service (137), NetBIOS datagram service (138), BOOTP/DHCP server (67), BOOTP/DHCP client (68), and TACACS (49).
- ip forward-protocol – to specify which type of broadcast packet is forwarded. Used for individual ports as opposed to **ip helper-address** which does all 8. You must use **ip forward-protocol udp [port]** for the ports you want to forward and then specify **no ip forward-protocol udp [port]** for the default ports you do not want forwarded.

```
router(config)#interface ethernet 0
```

```
router(config-if)#ip address 144.253.1.100 255.255.255.0
router(config-if)#ip helper-address 144.253.2.2
router(config-if)#ip forward-protocol udp 3000
router(config-if)#no ip forward-protocol udp 69
```

Configure IPX Standard Access List

1. generate the access list in global config mode
router(config)#access-list 800 deny 6e
router(config)#access-list 800 permit -1
2. apply the access list in interface mode
router(config)#interface ethernet 0
router(config-if)#ipx access-group 800 in

Configure IPX Extended Access List

Configure SAP Access List

1. generate the sap access list in global config mode
router(config)#access-list 1000 deny -1 47
router(config)#access-list 1000 deny 2e.0000.0000.0001 4
router(config)#access-list 1000 permit -1
2. apply the sap access list in interface mode
router(config)#interface serial 0
router(config-if)#ipx output-sap-filter 1000
3. (optional) configure the sap interval
router(config-if)#ipx sap-interval 10

Connecting IPX Networks using IP tunnels

1. configure the serial interface
router(config)#interface serial 0
router(config-if)#ip address 131.108.13.1 255.255.255.0
2. configure the tunnel interface
router(config)#interface tunnel 0
router(config-if)#ipx network 2130
3. tie the tunnel interface to the serial interface
router(config-if)#tunnel source serial 0
router(config-if)#tunnel destination 131.109.13.2

Verify IPX Filter Operation

- **show ipx interface** – verify the status of the interfaces that are routing ipx traffic, displays information on the ipx address of the interface, ipxwan status, ipx helper information, and sap and access list filtering
- **show ipx route** – view the ipx routing table, displays information on the following types of routers: connected primary network, internal network, static, floating static, ipxwan, rip, eigrp, nlsp, and external, and aggregate.
- **show ipx cache** – verify the ipx fast switching cache
- **show ipx servers** – display the available ipx servers, displays the type of service, the name of the servers, the network address of the server, and the distance in hops and ticks to the server. Displays the routers sap table
- **show ipx traffic** – verify ipx traffic, shows the number of packets transmitted and received. Includes broadcast, sap, routing, and watchdog information.

Configure Single Area OSPF

1. enable ospf on the router
router(config)#router ospf 1
2. assign the networks to ospf
router(config-router)#network 10.2.1.2 0.0.0.0 area 0
3. set the priority of the router, 0 –can't be DR, DR is the highest number
router(config-if)#ip ospf priority 0
4. modify the cost
router(config-if)#ip ospf cost 10

Verify Single Area OSFP

- show ip protocol – timers, filters, metrics, networks
- show ip route – routes known to router, one of best ways to determine connectivity
- sow ip opf interface – timer intervals, hello interval, neighbor adjacencies,
- show ip ospf – number of times spf algorithm has been run. Link-state update interval
- show ip ospf neighbor detail – detail list of neighbors, their priorities, their state(init, exstart, or full)
- show ip ospf database – display topological database

Configure Multi Area OSPF

ABR's

1. enable ospf on the router
router(config)#router ospf 1
2. assign the networks
router(config-router)#network 10.2.1.2 0.0.0.0 area 1
router(config-router)#network 10.64.0.2 0.0.0.0 area 0

Configuring Route Summarization on ABR

1. follow the steps in ABR's as listed above
2. summarize the routes for a specific area before injecting them into different areas
router(config-router)#area 0 range 172.16.96.0 255.255.224.0

Configuring Route Summarization on ASBR

1. follow the steps in ABR's as listed above
2. instruct the ASBR to summarize external routes
router(config-router)#summary-address 172.16.96.0 255.255.224.0

Configuring Stub and Totally Stubby Areas

1. follow the steps in ABR's as listed above
2. define an area as stub or totally stubby: put no-summary at end of command for totally stubby
router(config-router)#area 2 stub no-summary
3. (optional for ABR's only) define a cost for the default route
router(config-router)#area 2 default-cost 10

Verify Multi Area OSPF

- show ip ospf border-routers – displays the internal ospf routing table

- show ip ospf virtual-links – displays parameters of virtual links
- show ip ospf process-id – displays information about each area to which the router is connected, and indicates whether routes is a ABR, ASBR, or both
- show ip ospf database –contents of topological database

Configure Enhanced IGRP

1. enable eigrp
router(config)#router eigrp 1
2. indicate which networks are part of the eigrp system
router(config-router)#network 192.16.0.0
3. set the bandwidth on interface if different from T1
router(config)#serial 0
router(config-if)#bandwidth 56000

Configuring for IPX support

1. enable ipx routing
router(config)#ipx routing
2. define eigrp as the ipx routing protocol
router(config-ipx-router)#ipx router eigrp 1
3. indicate which networks are part of the eigrp autonomous system
router(config-router)#network 10
4. select the interface for sap incremental updates
router(config-if)#ipx sap-incremental eigrp 1

Verify Enhanced IGRP

- show ip eigrp neighbors – displays neighbors discovered by eigrp
- show ip eigrp topology – displays topology table, active/passive state or routes, number of successors, and the feasible distance to the destination
- show ip route eigrp – displays eigrp entries in routing table
- show ip protocols – shows eigrp as number, filtering and redistribution numbers, neighbors and distance
- show ip eigrp traffic – statistics on hello, updates, queries, replies, and ack's
- show ipx route – ipx routing table
- show ipx eigrp neighbors – ipx neighbors discovered by eigrp
- show ipx eigrp topology – topology table.

Configure ways to control route update traffic

- passive interface : prevents all routing updates for a given routing protocol from being sent to or received from a network via a specific interface
router(config)#router rip
router(config-router)#passive-interface serial 0
- default routes
router(config)#ip default-network 172.68.0.0
router(config)#ipx advertised-default-route-only 123
- static routes
router(config)#ip route 172.10.0.0 255.255.0.0
router(config)#redistribute static
- route update filtering

```
router(config)#access list 800 permit 6c  
router(config)#ipx router eigrp 100  
router(config-router)#network 6c  
router(config-router)#network 8e  
router(config-router)#distribute-list 800 out serial 0
```

Configure Route Redistribution

To redistribute igrp out rip:

```
Router(config)#router rip  
Router(config-router)#redistribute igrp 1  
Router(config-router)#passive-interface serial 0  
Router(config-router)#network 172.16.0.0  
Router(config-router)#default-metric 3
```

To redistribute rip out igrp:

```
Router(config)#router igrp 100  
Router(config-router)#redistribute rip  
Router(config-router)#passive-interface serial 0  
Router(config-router)#network 172.16.0.0  
Router(config-router)#default-metric 10 100 255 1 1500
```

Verify Route Redistribution

1. know your network topology
2. show the routing table
3. perform a trace
4. use trace and debug

Configure Connecting to an ISP with static, default, and BGP.

Static:

```
router(config)#ip route 172.0.0.0 255.255.255 S0
```

Default:

```
router(config)#ip route 0.0.0.0 0.0.0.0 S0
```

BGP:

```
router(config)#router bgp 100  
router(config-router)#network 19.0.0.0  
router(config-router)#neighbor 15.1.1.2 remote-as 200
```

Configure ISDN BRI

```
Router(config)#isdn switch-type basic-5ess  
Router(config)#interface isdn bri 0  
Router(config-if)#description "this is an isdn connection"  
Router(config-if)#isdn spid1 5551212  
Router(config-if)#isdn spid2 5551313
```

Configure DDR

1. configure interesting traffic using access-lists
router(config)#access-list 101 permit ip any any
2. place the access-list into a dialer group
router(config)#dialer-list 1 protocol ip list 101
3. apply the dialer-group to an interface
router(config-if)#dialer-group 1

Configure Dialer Properties

Configure Dialer Profiles

Verify DDR operation

- Ping/telnet -
- Show dialer – general diag information
- Show isdn active – calls in progress
- Show isdn status – show stats of isdn connection
- Show ip route – displays ip routes

Configure Dial Backup

Used for backup if the primary goes down.

```
Router(config)#interface serial 0
Router(config-if)#backup interface serial 1
Router(config-if)#backup delay 10 20
```

Used for backup if the primary becomes swamped.

```
Router(config)#interface serial 0
Router(config-if)#backup load 60 5
Router(config-if)#backup interface serial 1
```

Configure MultiLink PPP

```
Router(config-if)#ppp mulilink
Router(config-if)#dialer load-threshold load [outbound|inbound|either]
```

Configuring Snapshot routing

1. Configure the Client Router
 - a. specify a BRI interface
router(config)#interface BRI 0
 - b. configure the client router
snapshot client active-time quiet-time dialer
router(config-if)#snapshot client 5 360 dialer
 - c. define a dialer map
dialer map snapshot sequence-number name name dial-string
router(config-if)#dialer map snapshot 1 name server-router 15554441211
2. Configure the Server Router
 - a. specify a serial interface
router(config)#interface dialer 0
 - b. specify a dialer interface
snapshot server active-time dialer
router(config-if)#snapshot server 5 dialer
 - c. define a dialer map that includes the client routers
dialer map snapshot sequence-number name name dial-string
router(config-if)#dialer map snapshot 1 name client-router 17605651111

Configure IPX Spoofing

1. enter configuration mode for ISDN interface
router(config)#interface BRI 0
2. add a description of this interface (optional)
router(config-if)#description ISDN connectivity
3. define the SPID number if applicable, not required on switch type basic-5ess
router(config-if)#isdn spid1 555987601
router(config-if)#isdn spid2 555987602
3. enable IPX routing on this interface
router(config-if)#ipx network 123
4. disable IPX fast switching on this interface
router(config-if)#no ipx route-cache
5. set the router to respond to local watchdog packets
router(config-if)#ipx watchdog-spoof
6. enable SPX spoofing on this interface
router(config-if)#ipx spx-spoof
7. set the SPX idle time
router(config-if)#ipx spx-idle-time 300 (seconds) !
8. configure the interface to call multiple sites and to authenticate calls from multiple site
router(config-if)#dialer map ipx 123 name HQ broadcast 5552053
9. assign the dialer interface to a dialer group
router(config-if)#dialer-group 1
10. disable weighted fair queuing
router(config-if)#no fair-queue
11. set the encapsulation method
router(config-if)#encapsulation ppp
12. enable chap or pap
router(config-if)#ppp authentication chap
13. enable multilink ppp
router(config-if)#ppp multilink
14. enable the interface
router(config-if)#no shutdown

Extra stuff

```
interface dialer0
ip unnumbered loopback0
encapsulation ppp
dialer remote-name Remote0
dialer pool 1
dialer string 5551212
dialer-group 1
interface dialer1
ip unnumbered loopback0
encapsulation ppp
dialer remote-name Remote1
dialer pool 1
dialer string 5551234
dialer-group 1
interface bri 0
encapsulation PPP
dialer pool-member 1
ppp authentication chap
interface serial 0
```

```
ip unnumbered loopback0
backup interface dialer 0
backup delay 5 10
interface serial 1
ip unnumbered loopback0
backup interface dialer1
backup delay 5 10
```